

Phonak Virto M Order Form

Custom Hearing Instruments

Step 1: Order details

Account Number: 20

Hearing Clinic: _____

Delivery Address: _____

Contact Name: _____ Phone Number: _____

Email Address: _____





Date Ordered: _____ Date Required: _____

Step 3: Warranty/VIP service

4th year warranty (charges will apply)

VIP 24 hour service (\$57.75 incl GST)
Not available for Titanium products

Step 5: Product

	Virto M-Titanium L R	FitGuide values L: _____ R: _____
	Virto M-10 NW O L R	
	Virto M-312 NW O L R	
	Virto M-312 L R	

Step 6: Performance level

M90 M70 M50 M30

Note: Virto M Titanium models only available at 90 and 70 levels

Step 7: Power level

Left: M P SP UP*

Right: M P SP UP*

*UP only available with Virto-312 models

Step 8: Colours

Shell	Faceplate
06 Black*	06 Black***
19 White	22 Cocoa
21 Transparent	26 Pink
22 Cocoa	28 Brown
26 Pink	
28 Brown	*Only for Virto M-312 directional
R/B Red/Blue	**Only for Virto M-Titanium
U0 Titanium gray**	***Not for Virto M-312 NW O

Step 2: Patient information

Name: _____

Audiogram: (Required for AOV vent option)

	kHz	0.25	0.5	1	2	4
LEFT AC (dB HL)						
RIGHT AC (dB HL)						


Step 4: Scanned impression information

Scan/Serial Number:

L	_____
R	_____

Phonak recommends new impressions for scanned images >12 months

Step 9: Options

Fast order  Build product as standard version

Legend

--

 /

S

 = Standard

--

 = Optional

For selection options and codes see combination matrix on the back side.

Shell size	Smallest possible	<table border="1" style="display: inline-table;"><tr><td>S</td></tr></table>	S
	S		
Manually selected	Style: _____		
Vent size	AOV (enter audiogram)	<table border="1" style="display: inline-table;"><tr><td>S</td></tr></table>	S
	S		
	AOV-O (Virto M-Titanium)		
Manually selected	Left: _____ mm Right: _____ mm		
Wax system	Cerustop (CS)	<table border="1" style="display: inline-table;"><tr><td>S</td></tr></table>	S
	S		
Manually selected	Type: _____		
User controls	Standard controls	<table border="1" style="display: inline-table;"><tr><td>S</td></tr></table>	S
	S		
	EasyPhone & push button*		
	EasyPhone without push button*		
	MiniControl without push button*		
Volume control (VC)*			
	T-coil*		
Removal line (RF)	Transparent (21)**		
	Line extension +5 mm (RFE)		
Titanium surface	Extra retention (ERS)		
Accessories (Virto M-312)	TV Connector		
	Phonak Partner Mic™		
	Phonak RemoteControl		





*Not applicable for Virto M-312 **Standard for IIC & CIC

Special Instructions

Phonak Virto M Order Form

Custom Hearing Instruments

Combination matrix

		Virto M-Titanium 	Virto M-10 NW O 	Virto M-312 NW O 	Virto M-312 
Shell style		IIC, CIC	IIC, CIC, M, C, HS, FS	M, C, HS, FS	HS, FS
Push button	Standard	No push button (PX)	Push button (PM1)	No push button (PX)	Push button (PM1)
	Optional	Push button (PM1)	No push button (PX)	Push button (PM1)	-
Volume Control	Standard	-	No VC (VCX)	No VC (VCX)	No VC (VCX)
	Optional	-	Digital VC (VC3)	Digital VC (VC3)	Digital VC (VC3)
T-Coil	Standard	No T-coil (TX)	No T-coil (TX)	No T-coil (TX)	-
	Optional	T-coil passive (TP)	T-coil passive (TP) (not available in combination with VC)	T-coil passive (TP) (not available in combination with VC)	-
Magnetic switch function	Standard	MiniControl (DT5)	EasyPhone (DT4)	EasyPhone (DT4)	-
	Optional	EasyPhone (DT6)	MiniControl (DT3) No magnetic switch (RX)	No magnetic switch (RX)	-
Wax system	Standard	Cerustop (CS)	Cerustop (CS)	Cerustop (CS)	Cerustop (CS)
	Optional	-	HF3 (H3) HF4 (H4) Extended rec. tube (ER) Wax Spring (WS) Ext. Tube + Spring (WE) Wax guard not required (X)	HF3 (H3) HF4 (H4) Extended rec. tube (ER) Wax Spring (WS) Ext. Tube + Spring (WE) Wax guard not required (X)	HF3 (H3) HF4 (H4) Extended rec. tube (ER) Wax Spring (WS) Ext. Tube + Spring (WE) Wax guard not required (X)
Removal line	Standard	Removal line transparent (RF)*	Removal line transparent (RF)*	-	-
	Optional	-	Removal line transparent (RF)	Removal line transparent (RF)	Removal line transparent (RF)

*IIC & CIC will be standardly equipt with removal line

Titanium information

Vent Options

AOV = Acoustically Optimized Vent. Phonak will set the correct vent diameter and style in relation to Audiogram/shell geometry/feedback canceler and required low frequency gain. This is the recommended vent type.

AOV-O = Acoustically Optimized Vent-Open. This specific vent is more open and recommended for first time users and clients who are sensitive to occlusion.

Titanium FitGuide

Measure the possible insertion depth. The device will be built in accordance with the indicated FitGuide value. If the measurement falls between two numbers, please use the smaller number.

- Side M - For devices with M-receiver
- Side P - For devices with P-receiver
- Models with SP receiver will be built without FitGuide information

Impression Taking

Recommendation for taking deep impressions:

- Use EasyView Otoplast **1**
- Provide deepest impression as possible **2**
- Always fill the complete concha with impression material **3**
- Intertragal notch must be visible **4**
- Impression length must cover the evaluated FitGuide value **5**

